INSTRUCTIONS FOR USING SPR SOFTWARE THROUGH REMOTE DESKTOP CONNECTION (MAC OSX)

1) Open Microsoft's Remote Desktop App from your MAC or download it from the App Store if the App isn't already installed.



2) On Opening the App, we see a screen as below. Click on **New** to add the remote connection.



- 3) As shown in the screen below,
 - a. Enter a name in the Connection name field, to name the connection.
 - b. Enter the PC name as **spr.rrc.uic.edu**
 - c. Enter the User name as AD\Your_NetID.
 - d. Enter your ACCC Common Password in the Password field.
 - e. Leave the rest of the fields as specified.

0			California and
	2		Ste
w my Desktop			100
6 -	Eait Hemote Desktops -		
General Session	Hedirection		TRACE
			1450
Connection name	SPR Remote Desktop		1 LLAND
PC name	spr.rrc.uic.edu		
Gateway	No gateway configured		
Credentials		20-20	
User name	ADWET_ID		201811
Password	******		and the second
			CONTRACT OF
Resolution	Native		Star all
Colors	Highest Quality (32 bit)		PPP DE
Full screen mode	OS X native		hours
	Start session in full screen		a. n
NOTIFIC.	Scale content		1 1

- 4) Click on Redirection tab to add a local folder to the remote computer so as to analyze files from your local machine. Add details as shown below:
 - a. Specify any **name** for the folder.
 - b. Specify the path of the folder on your local machine.
 - c. Click Close.

Name	Path	
test	/Users/Softpedia/Desktop	
	Path Cancel OK	

5) Select the connection and click on Start as shown below:

New Star	Microsoft Remote Desktop	
My Des SPR Rem User na	sktops mote Desktop ame:	
		2

6) Click on Continue as shown below:

B	You are connecting to RDP he was verified through the cert certificate that was present i certificate is not a known, tru connection might not be sect	ost ' spr.rrc.uic.edu '! The certificate tificate chain to a self-signed root n the message, but that root usted root certificate. Your ure, do you want to continue?
	Show Certificate	Cancel

7) You will now be connected to your account on the remote SPR computer, as shown below:



8) Once you are finished using the SPR software on the remote machine, please **Log Off** from your account.